

Installation & Un-installation Manual for USB Pratirodh Single PC Version

CAUTION: SAME SETUP FILE IS USED FOR INSTALLATION AND UNINSTALLATION. PLEASE KEEP SETUP FILE SAFE AND DON'T DELETE AFTER INSTALLATION IS OVER. THE SAME FILE WILL BE USED FOR UNINSTALLATION.

Installation prerequisite and Guidelines

Ensure that the following requirements are met before you install

Microsoft Windows XP SP3 or higher


Microsoft .NET framework 4.0 or higher

Microsoft Visual C++ 2010 x86 Redistributable

Before starting the installation, please close all other applications and save all your work.

Note: If user is running 64 bit operating system, then USBPratirodh_X64.exe should be used to install the software and if user is using 32 bit operating system then USBPratirodh_X86.exe should be used to install the software.


User can see the System- > Properties (see screen below) to determine whether he/she is using 32bit/64bit Windows.




Installation Steps

Step 1:


Click on the USB Pratirodh Single PC Version setup, then following window will be shown.




If administrator clicks “Cancel” then setup will ask for confirmation.



If you click “Yes” then USB Pratirodh Single PC Version installation will be aborted by showing following window.



If administrator wants to proceed for the installation click on "Next".




Step 2:

Accept the License agreement and click on Next.



Step 3:

Installation path will be selected automatically. Just click on Next.



Step 4:


Enter the Administrator Name and Password here.

Administrator Name length should be 8 to 26 characters.

Password length should be 8 to 14 characters and it should be the combination of uppercase letters, Lowercase letters, digits and special characters. This Administrator Name and Password will be used for login to the USB Pratirodh Console, where administrator can add users and devices. Administrator should remember this name and password.

The Administrator password is used while uninstalling the solution.


Click on Next.



Step 5:


Here administrator has to give default password for users. Password length should be 8 to 26 characters and it should be the combination of uppercase letters, Lowercase letters, digits and special characters. When any user want to access his/her pen drive after knowing this password only he/she is able to access his/her device.

Click on Next.




Step 6

Now USB Pratirodh setup is ready to install, press the Install button.




Step 7

It will take some time to complete the installation. Please wait for some time.



After successful installation following screen will be appeared.

Click on Finish.



Un-installation Steps

Note: - Before starting the un-installation of USB Pratirodh Single PC Version, please make sure that all USB mass storage devices are removed from the USB port.


Please close the applications which belong to USBPratirodh Single PC Version if any. (For eg. USBPratirodh Admin Console and User manual for USB Pratirodh Single PC Version)

You can uninstall the solution from the setup which has used for installation.


Step 1

Double click on the setup. Then following windows will be shown.

This Uninstaller requires the administrator password. Please provide the Administrator Password and click on Next.




If you give wrong password the following message box will be popped up.



Click on **OK**.


Step 2

If the password is correct, then following window will be shown, click on "Remove".




Step 3

Then following window will be shown. Click on “Remove”.



Then is starts un-installation process.



Step 4

After successful un-installation the following window will be shown. Click on “Finish”.

