

Installation & Un-installation Manual for USB Pratirodh Single PC Version.

Installation prerequisite and Guidelines

Ensure that the following requirements are met before you install

Microsoft Windows XP SP3 or higher

Microsoft .NET framework 4.0 or higher


Microsoft Visual C++ 2010 x86 Redistributable

Before starting the installation, please close all other applications and save all your work.


Installation Steps

Step 1:


Click on the USB Pratirodh Single PC Version setup, then following window will be shown.




If administrator clicks No then USB Pratirodh Single PC Version installation will be aborted by showing following message.



If administrator wants to proceed for the installation click on Yes.



Click on Next.




Step 2:

Accept the License agreement and click on Next.



Step 3:

Installation path will be selected automatically. Just click on Next.



Step 4:

Enter the Administrator Name and Password here.

Administrator Name length should be 8 to 26 characters.

Password length should be 8 to 26 characters and it should be the combination of uppercase letters, Lowercase letters, digits and special characters. This Administrator Name and Password will be used for login to the USB Pratirodh Console, where administrator can add users and devices. Administrator should remember this name and password.


The Administrator password is used while uninstalling the solution.

Click on Next.

Step 5:


Here administrator has to give default password for users. Password length should be 8 to 26 characters and it should be the combination of uppercase letters, Lowercase letters, digits and special characters. When any user want to access his/her pen drive after knowing this password only he/she is able to access his/her device.

Click on Next.



Step 6


Now USB Pratirodh setup is ready to install, press the Install button.



Step 7

After successful installation following screen will be appeared.

Click on Finish.



Un-installation Steps


Note: - Before starting the un-installation of USB Pratirodh Single PC Version, please make sure that all USB mass storage devices are removed from the USB port .

You can uninstall the solution from the control panel and also from the start menu.


1. From Start Menu Un-installation Procedure:

Go to start menu and select USB Pratirodh and click on **Uninstall USB Pratirodh**

This Uninstaller requires the administrator password. Please provide the Administrator Password and click on Next.




If you give wrong password the following message box will be popped up.




Click on **OK**.


After five wrong attempts, Un-installation will be blocked. Please try again later.




If the password is correct, then starts un-installation process. After successful un-installation the following screen will appear to delete files/folders which are created by USB Pratirodh Single PC Version.



Click on **Yes**.




Click on **OK**.




2. From Control Panel Un-installation Procedure:

If you want to uninstall the solution from control panel, then following steps should be followed.

Go to Control Panel -> Change or Remove programs (for Windows XP) / Uninstall a Program (for other Windows versions) -> USB Pratirodh Single PC Version.



Select (for Windows XP)/ Right click (for other Windows versions) the USB Pratirodh Single PC Version.



Click on **Remove** (for Windows XP)/ **Uninstall** (for other Windows versions), then un-installation of USB Pratirodh Single PC version will be started, please follow the steps mentioned in [From Start Menu Un-installation Procedure](#) section.